


## 2.8 E-Mail Notification

### 2.8.1 E-mail Account Setup


1. In Multicam, click on the “**Configure**” icon.
2. Select “**General Setting**” -> “**E-Mail Setup**”.



3. Enter SMTP Server address. “**SMTP Server**” has to be provided by Internet Service Provider. It usually has the format of *smtp.mail.com*.
  4. Enter e-mail address in which e-mail alerts will be sent from. “**E-Mail From**” will appear as the sender when the e-mail is received.
  5. Enter e-mail address of recipients in “**E-Mail To**”. (For multiple recipients, add a coma between each e-mail address)
  6. Enter subject of e-mail alert.
  7. Enter customized e-mail contents in “**Text Content**”.
  8. Click on “**Test Mail Account**” icon to send out a test e-mail to see whether setup is correct.
  9. “**Attached Image Setup**” will include up to 6 snapshots in the e-mail alert.
  10. “**E-Mail Alerts Interval**” will prevent repeated e-mail alerts to be sent in the defined time interval.
  11. Default SMTP port is **25**, which is common for most SMTP servers. However, webmail providers such as Yahoo and Hotmail generally use different SMTP port. Check with e-mail provider for SMTP port number.
  12. Click “**OK**”.
- ✓ For detailed instruction, refer to p.84 of v8.4 User Manual

## 2.8.2 Event Notification Setup

1. In Multicam, click on the “**Configure**” icon.
2. Select “**General Setting**” -> “**System Configure**”.



3. Under “**Send Alerts Approach**”, Select “**E-mail**”.
4. Click “**OK**”.
5. Under “**Monitor Option**” box on the right, check “**Send Event Alerts**”.
6. Click on  and check the events for which e-mail alerts will be sent.
7. Click “**OK**”.

✓ For detailed instruction, refer to p.86 of v8.4 User Manual