

[FAQ]

How to set up e-mail alerts with Google Gmail?

Article ID: GV11-08-02-j

Release Date: 08/02/2011

Applied to

GV-System V8.3.2 or later

Question

How to set up e-mail alerts with Google Gmail on the GV-System?

Answer

To set up e-mail alerts with Gmail, you need to use GV-System of version V8.3.2 or later, and configure the e-mail settings.


How to do

To configure the e-mail settings, follow the steps below:


Note: The following instructions are based on GV-System V8.5, which has different menu options and dialog box design from previous versions.

1. On the GV-System, click the **Configure** button, select **System Configure** and select **Send Alerts Approach Setup**.

2. Select **E-Mail** and click **Setting**.



3. In the Mail Setup section, type the Gmail's URL address (smtp.gmail.com), and the sender and recipient's email addresses. You can add a semicolon between each e-mail address for multiple recipients.



4. Enable **SMTP Mail Server requires authentication**, and type the account name and password.
5. In the SMTP Server section, set the **SMTP Port** to be **465** and enable **SSL**.
6. Click **OK**.