6. Upgrade and Recovery

In this section, procedures to perform software upgrade and system recovery are as described below. Follow the procedures carefully when performing software upgrade or system recovery in order to prevent software errors and damages to the DVR system.

6.1 Software Upgrade

GeoVision provides free software upgrade. Keeping the GV-DVR System up-to-date will optimize system performance with maximum software capabilities. Refer to GeoVision/USAVision website or consult with GeoVision Technical Support for newest compatible software upgrade for your DVR system.

✓ Prior to software upgrade, make sure complete software and driver files are on the GV-DVR System. The upgrade files may be obtained via a GeoVision Main System Installation DVD or downloaded from USAVision FTP site. To obtain software and driver download or to request a copy of installation DVD, contact GeoVision Sales/Technical Support with the GV-DVR System barcode ready.

6.1.1 Remove Software

- 1. Close all GeoVision applications completely.
- 2. If there is any setting that requires backup, run **Fast Backup and Restore** (Section 5.5) to save current system settings.
- 3. On Windows desktop, click on "Start".
- 4. Click on "Control Panel".
- 5. Select "Add/Remove Programs".
- 6. Locate and double-click to remove "GeoVision Digital Surveillance System".

	Currently installed programs:	Show up <u>d</u> ates	Sort by: Name	j.	~
Change or Remove Programs	🔀 Adobe Reader 8	vess eme	Size	116.00MB	
	Control Center		Size	240.00MB	
	Commutatiview		Size	25.74MB	
	😼 GeoVision AAC				
			Size	0.07MB	
	🛼 Geo¥ision Digital Surveillance System		Size	532.00MB	
	Click here for support information.		Used	frequently	ş
			Last Used On	11/16/2010	
	To change this program or remove it from your computer, clic	k Change or Remove.	Change	Remove	
	GeoVision GV-LPR		Size	314.00MB	2
	😼 GeoVision H264				
	🔀 GeoVision JPEG				

- 7. Click "**OK**" when process completes.
- 8. Delete "**GVCombo**" folder under C:/. (Alternatively, the name of the folder may vary according to the GeoVision card model you are using. I.E. GV1480)

6.1.2 Remove Driver

- ✓ GV-NVR users may proceed to Section 6.1.4 Software Install directly
- Insert GeoVision Main System Installation DVD for new software and driver into DVD Rom.
 a. If the driver file is downloaded, run **DrvInst.exe** then proceed to step 14.
- 10. In the main menu, select "Install or Remove GeoVision GV-Series Driver".



6.1.4 Install Software

- 17. In the main menu, select "Install GeoVision System".
 - a. If the software file is downloaded, run **Setup.exe** then proceed to step 21.



- ✓ If GeoVision card mode used in the system is unknown, contact GeoVision Sales/Technical Support with barcode ready.
- 20. Select 1280*1024 (default) as resolution, then click "Next".

eoVision Digital Surveillance System - Instal		
Select Main Panel Resolution		24
Please select panel resolution		
○ 800*600	0 1920*1200	
0 1024*768	O 1280*800	
1280*1024 [Recommended]	O 1920*1080	
○ 1600*1200		
○ 1680*1050		

- ✓ Select higher resolution only if desktop resolution allows.
- Check "Add to the Startup" to allow Multicam to run automatically when Windows starts.
 Check "Install the Remote Control" if GV-Remote will be used on the system.
- 23. Click "Next".

Select Install Options	A-A
Please Enable/Disable options	
Add to the Startup	

24. Click "Next" to install in default program folder.

GeoVision Di	gital Surveillance System - InstallShield Wizard	
Choose D Select f	estination Location older where setup will install files.	
	Install GeoVision Digital Surveillance System to: C:\GV-NVR	<u>C</u> hange

25. Click "**Next**" to create default program folder under Program Menu.

alast Drogram Falder	Constant of the second s
elect Program Folder	Norma (
Please select a program folder.	
Setup will add program icons to the I folder name, or select one from the e	⁹ rogram Folder listed below. You may type a new existing folders list. Click Next to continue.
Program Folder:	
GV-NVR	
Existing Folders:	
Access Control	
Accessories	
Administrative Tools	
Control Center	
Nero	
BealVNC	
Startun	
TeamViewer 4	
Chinid	
omero	
	(Peak Next) Canaal
	<u>Cark</u> <u>Next</u> Cancer

- 26. When installation process is finished, select "**Yes, Restart My Computer Now**" to reboot the DVR system.
- 27. After GV-DVR System restarts, run FBR file from generated from step 2 above to reapply the settings.
- ✓ Perform Database Repair Utility (Section 5.6) to ensure all previous video recording is identified properly
- ✓ For detailed instruction, refer to v8.4 Installation Guide.